

RNA Antisense Purification (RAP) for mapping RNA interactions with chromatin

Jesse Engreitz^{1,2*}, Eric S. Lander^{2,3,4†}, and Mitchell Guttman^{5†}

¹Broad Institute of Harvard and MIT, Cambridge, MA 02142

²Division of Health Sciences and Technology, MIT, Cambridge, MA 02139

³Department of Biology, MIT, Cambridge, MA 02139

⁴Department of Systems Biology, Harvard Medical School, Boston, MA 02114

⁵Division of Biology and Biological Engineering, California Institute of Technology, Pasadena, CA 91125

*Correspondence to: engreitz@mit.edu

†These authors contributed equally to this work.

Running head: RNA Antisense Purification (RAP)

Summary

RNA-centric biochemical purification is a general approach for studying the functions and mechanisms of noncoding RNAs. Here, we describe the experimental procedures for RNA Antisense Purification (RAP), a method for selective purification of endogenous RNA complexes from cell extracts that enables mapping of RNA interactions with chromatin. In RAP, the user crosslinks cells to fix endogenous RNA complexes and purifies these complexes through hybrid capture with biotinylated antisense oligos. DNA loci that interact with the target RNA are identified using high-throughput DNA sequencing.

Keywords: RNA purification, chromatin, localization, lncRNA, hybrid capture

1 Introduction

Large noncoding RNAs (lncRNAs) – a class of RNAs >200 nucleotides long that do not encode proteins – are emerging as critical regulators of gene expression in mammals [1-5]. Inspired in part by classical examples such as the X-inactive specific transcript (Xist), a popular hypothesis is that many lncRNAs regulate gene expression by interacting with chromatin-regulatory proteins and recruiting them to specific DNA target sites. Indeed, recent work indicates that lncRNAs can interact with diverse chromatin regulators [6-9], localize to specific sites in the genome [10-12], and may even establish nuclear subdomains that contain the co-regulated DNA loci [12, 13]. Together, these observations highlight the need to map RNA-chromatin interactions to identify direct targets of lncRNA complexes.

Advances in RNA-centric biochemical purification have presented new opportunities for systematically mapping RNA interactions with chromatin [10-12]. RNA Antisense Purification (RAP) [12], as well as other recently developed methods like ChIRP [10] and CHART [11], captures a target RNA of interest through hybridization with antisense biotinylated oligos. By crosslinking endogenous macromolecular complexes prior to RNA capture, RAP allows for identification of proteins, RNA, and DNA loci that crosslink to and co-purify with the target RNA. Compared with previous approaches for examining RNA-chromatin interactions such as fluorescence *in situ* hybridization (FISH), RNA-centric biochemical purification enables genome-wide mapping of RNA-DNA interactions by coupling the protocol with high-throughput DNA sequencing (RAP-DNA). Thus, RAP provides an important tool for systematic interrogation of lncRNA function and mechanism.

Here, we describe the RAP technique for mapping RNA-chromatin interactions. Compared to similar protocols, the most distinctive and important feature of RAP is its use of long (120-nucleotide) capture probes tiled across the entire target RNA. This probe design strategy robustly captures any lncRNA and enables the use of stringent hybridization and wash conditions that dramatically reduce nonspecific interactions of

off-target nucleic acids or proteins [12]. We have applied this protocol to investigate ncRNAs in mouse embryonic stem cells and fibroblasts; the method is readily adapted to other systems where large quantities of cells can be obtained.

2 Materials

Prepare all buffers and solutions with nuclease-free water. Follow appropriate regulations when handling chemicals (*e.g.*, guanidine thiocyanate) and disposing waste.

2.1 Equipment

1. Sonication instrument (*e.g.*, Branson Sonifier with microtip) and chiller
2. Magnetic rack for 1.5 mL tubes (*e.g.*, Invitrogen DynaMag-2)
3. PCR machine and real-time quantitative PCR machine
4. Microcentrifuge
5. NanoDrop Spectrophotometer
6. Glass dounce
7. Heated mixer with 1.5 mL rack (*e.g.*, Eppendorf Thermomixer)

2.2 Solutions

Make stock solutions and store up to 6 months at room temperature, unless otherwise noted.

1. Scraping Buffer: PBS, 0.5% BSA Fraction V. Store at 4°C.
2. Cell Lysis Buffer: 10 mM HEPES pH 7.5, 20 mM KCl, 1.5 mM MgCl₂, 0.5 mM EDTA. Before use, add fresh 1 mM tris(2-carboxyethyl)phosphine (TCEP) and 0.5 mM phenylmethylsulfonyl fluoride (PMSF). Store at 4°C.
3. Nuclear Lysis Buffer: 20 mM HEPES pH 7.5, 50 mM KCl, 1.5 mM MnCl₂, 1% IGEPAL CA630 (NP-40), 0.4% sodium deoxycholate, 0.1% N-lauroylsarcosine. Before use, add fresh 1 mM TCEP and 0.5 mM PMSF. Store at 4°C.
4. 100× DNase Cofactor Solution: 250 mM MnCl₂, 50 mM CaCl₂.
5. 25× DNase Stop Solution: 250 mM EDTA, 125 mM EGTA.
6. Hybridization Buffer (1×): 20 mM Tris-HCl pH 7.5, 7 mM EDTA, 3 mM EGTA, 150 mM LiCl, 1% NP-40, 0.2% N-lauroylsarcosine, 0.1% sodium deoxycholate, 3

M guanidine thiocyanate, 2.5 mM TCEP. Prepare both 1× and 1.4× stock solutions.

7. Wash Buffer: 20 mM Tris-HCl pH 7.5, 10 mM EDTA, 1% NP-40, 0.2% N-lauroylsarcosine, 0.1% sodium deoxycholate, 3 M guanidine thiocyanate, 2.5 mM TCEP.
8. RNase H Elution Buffer: 50 mM Tris-HCl pH 7.5, 75 mM NaCl, 3 mM MgCl₂. Before use, add fresh 0.125% N-lauroylsarcosine, 0.025% sodium deoxycholate, 2.5 mM TCEP.
9. NLS Digestion Buffer: 20 mM Tris-HCl pH 7.5, 10 mM EDTA, 2% N-lauroylsarcosine, 2.5 mM TCEP.

2.3 Additional Materials and Reagents

1. NEBNext High-Fidelity PCR Master Mix (NEB)
2. T7 RNA Polymerase and 10× Buffer (NEB)
3. Murine RNase Inhibitor (NEB)
4. 100 mM ATP, CTP, GTP, UTP
5. DNA purification kit: DNA Clean and Concentrator-5 (Zymo)
6. RNA purification kits: RNA Clean and Concentrator-5 (Zymo), RNeasy Mini (Qiagen)
7. TURBO DNase (Invitrogen)
8. Multiple-temperature reverse-transcription reagents (*e.g.*, AffinityScript Reverse Transcriptase and Buffer from Agilent)
9. Cell scraper
10. Disuccinimidyl glutarate (Pierce)
11. 16% Formaldehyde solution in 10-mL ampules (Pierce)
12. 2.5 M Glycine solution
13. BSA Fraction V
14. MyONE Streptavidin C1 magnetic beads (Invitrogen)
15. MyONE SILANE magnetic beads (Invitrogen)
16. 100 mM dithiothreitol (DTT)
17. 10× RT Random Primers (Applied Biosystems)

18. RT-qPCR reagents and PCR primers
19. NEBNext Ultra DNA Library Prep Kit and Multiplex Primers (NEB)

3 Methods

3.1 Assay Design

1. Choose a target RNA of interest.
2. Choose appropriate negative control target sequences. For example, scramble the sequence of the target RNA to create a GC-content-matched control that does not exist in the cell. Alternatively, purify mRNAs, which likely do not interact with chromatin outside of their own genomic loci.
3. Choose appropriate positive control targets to aid in optimizing lysis and purification conditions (see **Note 1**).

3.2 Probe Design

1. Design 90- to 120-nucleotide capture probes antisense to the target RNA sequences. Shorter probes (50-90 nucleotides) can also be used, provided GC content is >50%. Probes can be tiled across the entire transcript (*e.g.*, each 120-nucleotide probe overlaps the next probe by 105 nucleotides), or they can be divided into two non-overlapping probe pools (even and odd) for additional specificity (see **Note 2**).
2. Omit probes that may hybridize to off-target sequences. Remove probes that contain more than 8 bases of any repetitive or low-complexity sequences as defined by RepeatMasker and Tandem Repeat Finder (these annotations can be viewed on the UCSC Genome Browser at <http://genome.ucsc.edu>). Remove probes that contain homo-polymers of more than 8 bases. Remove probes that align to other regions in the genome with 25 or more matching bases (*e.g.*, with BLAT).
3. Choose and validate RT-qPCR primers spanning a short amplicon (<90 bases) on the target RNA, and omit probes that overlap this region. This will enable qPCR measurement of purification yields and enrichments without confounding signal from residual amounts of the probes themselves.

3.3 Probe Generation

The protocol below uses oligonucleotide library synthesis technology to simultaneously generate pools of ssDNA probes targeting many different RNAs. Each probe set is tagged with unique PCR primers that allow for enrichment of specific probe sets from the total pool. Probe sets are *in vitro* transcribed and then reverse transcribed with biotinylated primers to generate single-biotin ssDNA probes (see **Note 3**). For alternative probe synthesis and amplification strategies, see **Note 4**.

1. For each probe set, design unique PCR tags (20 base-pairs) with 65 °C annealing temperatures (hereafter, Left Tag Primer and Right Tag Primer). Append the PCR tags to the ends of each probe in a given probe set such that the Left Tag Primer is on the 5' end of the oligo sequence and the Right Tag Primer is on the 3' end of the oligo sequence (which is itself antisense to the target RNA).
2. Order the pool of ssDNA oligos from an oligo library synthesis company (*e.g.*, CustomArray, Inc.).
3. Resuspend the lyophilized oligo pool in water to a final concentration of 10 nM. Aliquot and store at -20 °C.
4. Order primers: for each probe set, order (i) Left Tag and Right Tag primers; (ii) T7-Left Tag and T7-Right Tag Primers, which are comprised of Left Tag and Right Tag Primers each following a T7 promoter sequence (*e.g.*, GGATTCTAATACGACTCACTATAGGG-Left Tag Primer); and (iii) 5'-biotinylated Left Tag and Right Tag Primers.
5. For each probe set, enrich the component probes from the oligo pool using the unique PCR tags. Set up PCR reaction on ice:
 - 1 µL of Oligo Pool (10 nM)
 - 1 µL of Tag Primer Left (25 µM)
 - 1 µL of Tag Primer Right (25 µM)
 - 25 µL of NEBNext High Fidelity 2× Master Mix (NEB)
 - 22 µL H₂O
6. Run PCR program:
 - 98 °C for 30 sec

- 25-35 cycles of 98 °C for 10 sec, 65 °C for 20 sec, 72°C for 20 sec
 - 72 °C for 60 sec
 - 4 °C hold
7. Clean the PCR product using a DNA purification column according to manufacturer's protocol. Measure DNA yield using a NanoDrop spectrophotometer. Examine the dsDNA product on an agarose gel. If necessary, repeat PCR varying the annealing temperature, oligo pool amount, or number of cycles until the reaction produces a single clean band at the appropriate size (see **Note 5**).
8. For each probe set, perform a second round of PCR amplification to add the T7 promoter sequence (GGATTCTAATACGACTCACTATAGGG). Set up two PCR reactions to add the T7 promoter sequence onto one or the other end of the dsDNA template, allowing for generation of both sense and antisense probes. To generate antisense ssDNA probes that capture the target RNA, for example, use Tag Primer Left with T7-Tag Primer Right.
- 1 µL of diluted enriched dsDNA (~1 nM)
 - 2 µL of primer mix (mix contains 25 µM of each primer)
 - 25 µL of NEBNext High Fidelity 2× Master Mix
 - 22 µL H₂O
9. Run PCR program:
- 98 °C for 30 sec
 - 12-15 cycles of 98 °C for 10 sec, 65 °C for 20 sec, 72°C for 20 sec
 - 72 °C for 60 sec
 - 4 °C hold
10. Clean the PCR product using a DNA purification column according to manufacturer's protocol. Measure DNA yield using a NanoDrop spectrophotometer. Examine the dsDNA product on an agarose gel. If necessary, repeat PCR varying the annealing temperature or number of cycles until the reaction produces a single clean band at the appropriate size. If necessary, perform multiple PCR reactions to generate >250 ng of dsDNA T7 template for *in vitro* transcription.

11. For each probe set, set up a 40 μL *in vitro* transcription reaction:
 - 24.2 μL T7 DNA template (250 ng total)
 - 4 μL 10 \times RNA Polymerase Reaction Buffer
 - 2 μL each 100 mM ATP, CTP, GTP, UTP
 - 3 μL T7 RNA Polymerase
 - 0.4 μL 100 mM DTT
 - 0.4 μL Murine RNase Inhibitor
12. Mix well by pipetting. Incubate at 37 $^{\circ}\text{C}$ overnight.
13. Next day, transfer reaction to 85 $^{\circ}\text{C}$ for 3 minutes. Afterward, place immediately on ice for 1 min.
14. To digest dsDNA templates, add 42 μL H_2O , 10 μL TURBO DNase Buffer, and 8 μL TURBO DNase (100 μL total volume). Incubate at 37 $^{\circ}\text{C}$ for 15 minutes.
15. Purify RNA, using sufficient ethanol to precipitate the ~ 150 -nucleotide RNA fragments. For example, use an RNeasy Mini column (maximum capacity 100 μg RNA): Add 3.5 \times RLT (350 μL) to sample and mix well. Add 1.5 \times 100% ethanol (775 μL) to sample-RLT mixture and mix well. Transfer 700 μL to the RNeasy Mini column, and spin for 15 seconds at $>8,000\times g$. Discard flow-through and repeat with remaining sample. Add 500 μL Buffer RPE to column and spin for 15 seconds. Discard flow-through. Repeat wash step. Transfer column to fresh collection tube and spin for 2 minutes to remove residual Buffer RPE. Transfer column to 1.5 mL tube; add 30 μL H_2O and spin for 1 minute to elute.
16. Measure RNA yield with a NanoDrop and dilute to a convenient concentration (*e.g.*, 1 $\mu\text{g}/\mu\text{L}$). Ideally yield should be >50 μg for a 40 μL reaction.
17. Run RNA on gel to confirm the correct size of the *in vitro* transcription product.
18. To generate ssDNA, set up a 200 μL reverse transcription reaction:
 - 120 μL RNA template (10 μg) + H_2O
 - 20 μL 100 μM 5'-biotinylated Left Tag Primer
 - 20 μL 10 \times AffinityScript Buffer
 - 20 μL 100 mM DTT
 - 8 μL 100 mM dNTP (25 mM each)
 - 10 μL AffinityScript Reverse Transcriptase Enzyme

- 2.5 μ L RNase Inhibitor
19. Incubate at 55 °C for 50 minutes, then 75 °C for 5 minutes.
 20. To degrade RNA templates, add 0.1 \times (20 μ L) 1 M NaOH. Incubate at 75 °C for another 10 minutes.
 21. Add 0.1 \times (20 μ L) 1 M acetic acid to neutralize.
 22. Clean up the ssDNA product and eliminate the unused primer by size selection.
For example, use a Zymo RNA Concentrator-5 column: Add 2 \times volume RNA Binding Buffer (480 μ L) and mix well; add 1.9 \times original volume 100% ethanol (456 μ L) and mix well. Transfer 700 μ L to column; spin at 12,000 \times g for 1 minute. Discard flow-through and repeat with remaining sample. Add 400 μ L RNA Prep Buffer; spin for 30 seconds and discard flow-through. Add 700 μ L RNA Wash Buffer; spin and discard flow-through. Repeat the wash step with 400 μ L RNA Wash Buffer. Transfer column to clean collection tube and spin for 2 minutes. Transfer column to a 1.5 mL tube, add 30 μ L of water, and spin at 10,000 \times g for 1 minute to elute.
 23. Measure the yield with a NanoDrop. Ideal yield should be \sim 3 μ g ssDNA for a 200 μ L reverse transcription reaction.
 24. Freeze biotinylated ssDNA probe until use.

3.4 Cell Harvesting and Crosslinking

This protocol describes the steps for adherent cells. To adapt for suspension cells, spin cells between steps and decant supernatant to exchange buffers.

1. Before starting, heat one aliquot PBS at 37 °C and chill one aliquot at 4 °C (see below for volumes).
2. Grow adherent cells on 15-cm tissue culture plates. Before crosslinking, carefully split and count one plate (see **Note 6**).
3. Resuspend 50 mg of disuccinimidyl glutarate (DSG) in 306 μ L room-temperature DMSO to create a 0.5 M stock solution.
4. Dilute DSG to 2 mM in room-temperature PBS. Prepare 7 mL of 2 mM DSG for each 15-cm plate.

5. Remove media from cells. Rinse cells in plate with 10 mL room temperature PBS. Discard PBS.
6. Add 7-10 mL of 2 mM DSG solution and rock plates gently at room temperature for 45 minutes to crosslink (see **Note 7**).
7. Immediately before using, prepare a 3% formaldehyde solution in PBS preheated to 37 °C. Use a fresh ampule of 16% formaldehyde (Pierce).
8. Remove DSG solution from cells and rinse once with room temperature PBS.
9. Add 7 mL warmed 3% formaldehyde solution to cells. Incubate at 37 °C for 10 minutes, gently rocking by hand every 3 minutes.
10. Quench formaldehyde crosslinking by adding glycine to a final concentration of 500 mM. Incubate at 37 °C for 5 minutes.
11. Discard formaldehyde waste in appropriate disposal container.
12. Rinse cells three times with cold PBS. Avoid dislodging cells from plate.
13. After last wash, add 2 mL of ice-cold Scraping Buffer to each 15-cm plate. From this point, keep cells at 4 °C.
14. Scrape cells from plate and transfer to a 15-mL Falcon tube.
15. Centrifuge at 1,000× *g* at 4 °C for 5 minutes to pellet cells.
16. Discard supernatant and resuspend pellet in 1 mL ice-cold Scraping Buffer to break up the pellet. Add more Scraping Buffer if necessary for convenient aliquoting (*e.g.*, add 1 mL of Scraping Buffer for every 20 million cells).
17. Aliquot cells into microcentrifuge tubes (20 million cells each) and spin at 2,000× *g* at 4 °C for 5 minutes.
18. Remove supernatant and flash freeze pellets in liquid nitrogen. Store until cell lysis at -80 °C.

3.5 Cell Lysis

All steps and buffers should be cooled to 4 °C.

1. Thaw cell pellets by completely resuspending 20 million cells in 1 mL Cell Lysis Buffer (add TCEP and PMSF fresh) in a 1.5 mL microcentrifuge tube.
2. Pellet cells by spinning at 3,300× *g* for 7 minutes. Remove supernatant.

3. Gently resuspend swelled cells in 1 mL ice cold Cell Lysis Buffer pre-mixed with 0.1% NP-40. Incubate on ice for 10 minutes.
4. Transfer to an ice-cold glass dounce of appropriate size (*e.g.*, 2 mL). Homogenize cell lysate by douncing 20×.
5. Transfer cells back to a microcentrifuge tube and pellet nuclei by spinning at 3,300× *g* for 7 minutes. Remove supernatant.
6. Resuspend nuclei in 1 mL of Nuclear Lysis Buffer (add TCEP and PMSF fresh). Incubate on ice for 10 minutes.
7. Sonicate using a Branson Sonifier fitted with a microtip using 5 Watts of power for 2 minutes in pulses: 0.7 seconds on, 3.3 seconds off (see **Note 8**).
8. Split sample into two separate microcentrifuge tubes, each with 500 µL lysate.
9. To each, add 6 µL of 100× DNase Cofactor Solution and 50-100 µL TURBO DNase (see **Notes 9 and 10**). Mix by pipet.
10. Transfer to a 37 °C heat block and incubate for 10-15 minutes (see **Note 10**).
11. Return sample to ice and immediately halt DNase reaction by adding 24 µL of DNase Stop Solution. Mix immediately by pipetting.
12. Remove and save a 5 µL aliquot of lysate (pre-clear).
13. Mix ~600 µL of lysate with 1.5 mL of 1.4× concentrated Hybridization Buffer.
14. Clear lysate by spinning at maximum speed (16,000× *g*) for 10 minutes.
15. Remove and save a 5 µL aliquot of lysate (post-clear).
16. Flash-freeze aliquots of lysate in liquid nitrogen and store at -80 °C.
17. To check quantities and sizes of RNA and DNA in saved aliquots of lysate (Steps 12 and 15 above), first add 40 µL of NLS Digestion Buffer, 2.5 µL of 5 M NaCl, and 2.5 µL Proteinase K (see **Note 11**), and incubate at 65°C for 60 minutes.
18. Clean and purify nucleic acids as desired (*e.g.*, ethanol precipitation).
19. Split in half; treat half with DNase and half with RNase, and incubate for 37 °C for 10 minutes.
20. Clean and purify nucleic acids. Elute in 10 µL H₂O.
21. Quantify DNA yields with a NanoDrop spectrophotometer (see **Note 12**).
22. Assess fragment sizes with the Agilent Bioanalyzer (High-Sensitivity DNA and RNA Pico kits). Ideal fragment sizes (pre-clear) are shown in **Figure 1**.

3.6 Lysate Preparation

1. Thaw lysate corresponding to 5 million cells for each sample (see **Note 13**).
2. Aliquot out 100 μ L MyONE Streptavidin C1 magnetic beads for each purification from 5 million cells.
3. Wash beads twice in 0.5 \times original bead volume Hybridization Buffer, using a magnetic rack to capture beads and remove wash buffers each time. When separating magnetic beads from solution, place sample on magnet and wait 1-2 minutes before proceeding to allow beads to completely separate.
4. Resuspend beads in 0.25 \times bead volume Hybridization Buffer. Add beads to lysate (*i.e.*, 25 μ L concentrated beads to 1 mL of lysate containing 5 million cells).
5. Incubate at 37 $^{\circ}$ C for 20-30 minutes, shaking.
6. Magnetically separate and transfer supernatant (streptavidin-cleared lysate) to a clean tube. Repeat this step to completely remove beads.
7. Save 5 μ L of pre-cleared lysate (0.5% total input) on ice as DNA input.
8. Re-warm lysate to 37 $^{\circ}$ C, then proceed immediately to hybridization.

3.7 Hybridization, Capture, Wash, Elute

Prepare wash and elution buffers beforehand. Equilibrate solutions to the indicated temperatures before adding to samples.

1. Aliquot out 50 pmol of biotinylated ssDNA probe for each purification from 5 million cells.
2. Denature probe in H₂O at 85 $^{\circ}$ C for 3 minutes and then transfer immediately to ice.
3. Add probe to lysate, mix, and immediately transfer to a 37 $^{\circ}$ C Thermomixer.
4. Incubate at 37 $^{\circ}$ C for 2-3 hours, shaking at 1,200 r.p.m.
5. Just before use, aliquot out 500 μ L of Streptavidin C1 magnetic beads for each sample. Wash twice in 0.5 \times bead volume Hybridization Buffer, then resuspend in 0.25 \times bead volume Hybridization Buffer. Add beads to sample and incubate at 37 $^{\circ}$ C for 15-30 minutes, shaking.

6. Magnetically separate and then remove supernatant. Optional: save supernatant for quality control steps (see **Note 14**).
7. Resuspend beads in 1× original bead volume (500 µL) Wash Buffer, then incubate at 45 °C for 3-10 minutes while washing other samples. Wash a total of 6 times. When removing final wash: place on magnet, remove liquid, spin down tube briefly, and remove the last drops of wash buffer with a fine tip.
8. Wash with 1× bead volume RNase H Elution Buffer (add TCEP and detergents fresh).
9. Wash with 100 µL RNase H Elution Buffer (add TCEP and detergents fresh).
Transfer samples to new tube before removing the final wash.
10. To elute, add 55 µL RNase Elution Buffer and 7.5 µL RNase H to each sample.
11. Incubate at 37 °C for 30 minutes, shaking.
12. Remove and save eluate.
13. Add 62.5 µL Hybridization Buffer and incubate at 37 °C for 5 minutes, shaking.
14. Remove eluate and combine with previous eluate.
15. Magnetically separate the combined eluates once more and transfer to a new tube to remove any residual beads and attached ssDNA probe.
16. Add 312.5 NLS Digestion Buffer, 50 µL 5 M NaCl, and 12.5 µL Proteinase K to each sample and to the saved input sample. Proceed to DNA or RNA analysis section. Alternatively, divide sample for both RNA and DNA analysis (see **Note 15**); for example, use 50 µL for RNA analysis and 450 µL for DNA analysis.

3.8 RNA Analysis

1. Mix well, and incubate tubes for 1 hour at 65 °C to digest protein and reverse formaldehyde crosslinks.
2. Clean and purify nucleic acids (*e.g.*, using Zymo RNA Concentrator-5 columns). Elute in 15 µL H₂O.
3. Add 2 µL 10× TURBO DNase Buffer, 2 µL TURBO DNase to digest genomic DNA, and 1 µL Exonuclease I to digest residual ssDNA probe. Incubate at 37 °C for 15 minutes.

4. Clean and purify nucleic acids (*e.g.*, using Zymo RNA Concentrator-5 columns). Elute in 12.2 μL H_2O .
5. Set up reverse transcription reaction:
 - 12.2 μL RNA
 - 2 μL 10 \times RT Random Primers
 - 2 μL 10 \times AffinityScript Buffer
 - 2 μL 100 mM DTT
 - 0.8 μL 100 mM dNTPs (25 mM each)
 - 1 μL AffinityScript RT Enzyme
6. Mix. Incubate at 25 $^{\circ}\text{C}$ for 10 minutes, 55 $^{\circ}\text{C}$ for 50 minutes, and 70 $^{\circ}\text{C}$ for 15 minutes.
7. Place samples on ice. Dilute cDNA by adding 180 μL H_2O .
8. Analyze cDNAs using quantitative real-time PCR to determine enrichment and yield of the target RNA (see **Note 16**). Primers should include one or more primer pairs for the target RNA as well as multiple primer pairs targeting other abundant RNAs (*e.g.*, 18S rRNA, U1 snRNA).
9. Calculate enrichment as the ratio of the amount of the target RNA in the target purification versus negative-control purification, normalized to the ratio of the signal of abundant RNAs in the target purification versus negative-control purification. Calculate yield as the ratio of the amount of the target RNA in the target purification versus the input, accounting for the fraction of input saved in Section 3.6 Step 7.

3.9 DNA Analysis

1. Mix well, and incubate tubes overnight at 60 $^{\circ}\text{C}$ to digest protein and completely reverse formaldehyde crosslinks.
2. Clean and purify DNA.
3. If desired, analyze genomic DNA using quantitative real-time PCR to determine enrichment and yield of target DNA (see **Note 17**).
4. Generate DNA sequencing libraries for high-throughput DNA sequencing using the NEBNext Ultra DNA Library Prep Kit for Illumina using the manufacturer's

protocol. Sequence the DNA libraries to generate ~20 million reads for the RAP samples and 30-80 million reads for the input samples (see **Note 18**).

4 Notes

1. As a positive control, we suggest purifying the highly abundant U1 snRNA. In mouse cells (*Mus musculus*), use the following three 5'-biotinylated probes: (1) CAGGGGAGAGCGCGAACGCAGTCCCCCACTACCACAAATTATGCAGT CGA, (2) GTTTCCCGCATTTGGGGAAATCGCAGGGGTCAGCACACCCCAAAGTGCAA, (3) TGGGTGAGCCTCGCCCTGGGAAAACCACCTTCATGATCATGGTATCTCC.
2. Nonspecific hybridization of probes to off-target RNAs or DNA loci is a major concern for hybridization-based purification strategies. RAP uses highly denaturing and stringent hybridization conditions to ensure capture specificity. However, nonspecific interactions are difficult to predict and will be different for each new target RNA, and so we recommend using two independent probe sets in an even/odd design to provide additional confidence in RNA-chromatin interactions identified with RAP.
3. Single-stranded DNA probes provide better specificity than the RNA probes used in previous iterations of this protocol [12].
4. An alternative strategy for obtaining RAP probes is to order 5' biotinylated oligos from a commercial supplier. Compared to the protocol presented above, ordering ready-to-use biotinylated probes from a commercial supplier potentially provides a faster and cheaper alternative for obtaining large amounts of a smaller number of probes.
5. In some cases, specific amplification of subsets of the oligo pool can be challenging, depending on the quality of the oligo synthesis and the complexity of the oligo pool. We typically order oligo pools with 12,000 unique sequences from Custom Array, Inc. and achieve robust amplification of full-length product.

6. Accurate cell counts are critical for maintaining consistency between cell and lysate batches because cell numbers affect the efficiency of the sonication and DNase treatment during lysis. We typically harvest and crosslink 100-200 million cells in parallel and freeze multiple 20-million cell pellets; one of these pellets is spent to optimize lysis conditions, and the rest are used for purification experiments.
7. For some cell types, reducing the crosslinking amount (*e.g.*, to 2% formaldehyde) or reducing the length of the DSG treatment may allow for better lysis and solubilization.
8. Samples should be kept cold during sonication, for example by holding the sample in a 4 °C chilling rack or ice bath. Depending on the length of sonication and the efficiency of the cooling strategy, longer breaks between sonication pulses may help to keep samples cool.
9. TURBO DNase works better than standard DNase I here because it works more robustly in high-salt solutions.
10. Optimization of the lysis conditions (amount of sonication, amount/timing of DNase) is a critical step in establishing the protocol for the first time. The length of sonication might vary from 1-4 minutes, and DNase treatment might vary from 10 to 20 minutes, depending on cell number, ploidy, and crosslinking strength. To optimize DNase timing and conditions, remove 5 µL lysate aliquots every 2-4 minutes, quench with EDTA and EGTA on ice, and assay RNA and DNA sizes for each time point as described in the protocol. In optimizing the lysis conditions, the goals are (i) to solubilize as much chromatin as possible (assayed by comparing DNA concentrations from lysate before and after the clearing spin in Section 3.5 Step 14), (ii) to digest the DNA to appropriate fragment sizes for DNA sequencing (with a significant fraction of fragments in the range of 100-600 basepairs as assayed by gel electrophoresis or Bioanalyzer), and (iii) to avoid severe degradation of cellular RNA (assayed by gel electrophoresis or Bioanalyzer). We recommend trying several different lysis conditions and comparing the results obtained when performing RAP on a positive control target RNA. If an appropriate combination of solubilization and RNA/DNA fragment

sizes cannot be obtained by varying the amount of sonication or DNase, then reducing the strength of the crosslinking may be necessary.

11. The Hybridization Buffer contains 3 M guanidine thiocyanate, which precipitates sodium dodecyl sulfate (SDS) detergent; do not use SDS in buffers in place of N-lauroylsarcosine. High concentrations of guanidine thiocyanate at high temperature will denature dsDNA fragments: in order to avoid denaturing dsDNA, dilute final guanidine thiocyanate concentration 8-fold (to less than 375 mM final concentration) during any Proteinase K digestion.
12. Accounting for the dilution of the lysate between the pre-clear and post-clear aliquots, we typically find that the post-clear aliquots contains >50% of the DNA of the pre-clear aliquot, indicating successful solubilization of chromatin.
13. We have found that 5 million cells per sample is more than enough to map RNA-chromatin interactions for abundant noncoding RNAs like Xist or U1; for lower-abundance RNAs, more cells may be necessary. In this case, scale up probe amounts and reaction volumes accordingly.
14. When establishing and troubleshooting the assay, it may be useful to save the supernatant, treat with Proteinase K, and isolate RNA and/or DNA to examine (i) the integrity of the RNA at the end of the hybridization, (ii) the amount of target RNA/DNA remaining in the supernatant after capture, and (iii) the amount of probe remaining in the supernatant after capture.
15. RNA analysis should be used initially to validate capture of the target RNA. After establishing the reproducibility of the assay, RNA analysis can be skipped and the entire sample can be used for DNA analysis.
16. RNA enrichments are typically in the range of 100-1,000-fold versus negative controls. RNA yields are typically in the range of 10-80%, depending on the target RNA. If low RNA (or DNA) enrichments are observed with high yield, one possible reason is that crosslinked macromolecular complexes are too large due to over-crosslinking or insufficient sonication; try decreasing crosslinking or increasing sonication. If low RNA (or DNA) enrichments are observed with low yield, then there are multiple possibilities to consider. First, RNA may be degraded throughout the process, leading to poor capture; to address this, examine

- RNA integrity and yields at each intermediate step by RT-qPCR and/or visualization of RNA sizes with the Bioanalyzer. Second, the probe set may not properly capture the target RNA even with acceptable RNA integrity; to test this, use the same probe set to capture the target RNA in purified total RNA using the same protocol, and/or test the protocol in lysate using an abundant positive control RNA.
17. In initial experiments, measure DNA yields and enrichments using quantitative PCR to validate that the experiment worked before moving immediately to DNA sequencing. Primers should include one or more primer pairs that measure genomic DNA close to but not overlapping the target gene locus; these regions should be strongly enriched (>100 -fold) compared to input after normalizing to other locations in the genome. An appropriate negative control for this assay is comparing RAP with antisense probes to RAP with sense probes, which will capture DNA at the target locus but not RNA; the antisense probes should enrich more strongly for genomic DNA close to the target gene locus. Depending on the abundance of the target RNA, it may be necessary to use the entire DNA sample for qPCR, rather than saving some for DNA sequencing, to ensure that the DNA levels are high enough to meet the threshold for qPCR quantification.
 18. Proper analysis of the data, including identification of RNA-chromatin interaction sites and calculation of enrichments across different regions of the genome, requires deep sequencing of the input library because DNA fragment density can vary substantially across the genome [12].

5 References

1. Carninci P, Kasukawa T, Katayama S, et al. The transcriptional landscape of the mammalian genome. *Science* 2005;309(5740):1559–63.
2. Guttman M, Amit I, Garber M, et al. Chromatin signature reveals over a thousand highly conserved large non-coding RNAs in mammals. *Nature* 2009;458(7235):223–7.
3. Guttman M, Garber M, Levin JZ, et al. Ab initio reconstruction of cell type-specific transcriptomes in mouse reveals the conserved multi-exonic structure of lincRNAs. *Nat Biotechnol* 2010;28(5):503–10.

4. Cabili MN, Trapnell C, Goff L, et al. Integrative annotation of human large intergenic noncoding RNAs reveals global properties and specific subclasses. *Genes Dev* 2011;25(18):1915–27.
5. Derrien T, Johnson R, Bussotti G, et al. The GENCODE v7 catalog of human long noncoding RNAs: analysis of their gene structure, evolution, and expression. *Genome Res* 2012;22(9):1775–89.
6. Guttman M, Donaghey J, Carey BW, et al. lincRNAs act in the circuitry controlling pluripotency and differentiation. *Nature* 2011;477(7364):295–300.
7. Tsai MC, Manor O, Wan Y, et al. Long noncoding RNA as modular scaffold of histone modification complexes. *Science* 2010;329(5992):689–93.
8. Nagano T, Mitchell JA, Sanz LA, et al. The Air noncoding RNA epigenetically silences transcription by targeting G9a to chromatin. *Science* 2008;322(5908):1717–20.
9. Zhao J, Sun BK, Erwin JA, Song JJ, Lee JT. Polycomb proteins targeted by a short repeat RNA to the mouse X chromosome. *Science* 2008;322(5902):750–6.
10. Chu C, Qu K, Zhong FL, Artandi SE, Chang HY. Genomic Maps of Long Noncoding RNA Occupancy Reveal Principles of RNA-Chromatin Interactions. *Mol Cell* 2011;
11. Simon MD, Wang CI, Kharchenko PV, et al. The genomic binding sites of a noncoding RNA. *Proc Natl Acad Sci U S A* 2011;108(51):20497–502.
12. Engreitz JM, Pandya-Jones A, McDonel P, et al. The Xist lncRNA exploits three-dimensional genome architecture to spread across the X chromosome. *Science* 2013;341(6147):1237973.
13. Hacisuleyman E, Goff LA, Trapnell C, et al. Topological organization of multichromosomal regions by the long intergenic noncoding RNA Firre. *Nat Struct Mol Biol* 2014;21(2):198–206.

Figure Legends

Figure 1. DNA and RNA fragment sizes after lysis.

(A) Example distribution of DNA fragment sizes (pre-clear). Sizes are measured with the High Sensitivity DNA Bioanalyzer assay. (B) Example distribution of RNA fragment sizes (pre-clear). Sizes are measured with the RNA 6000 Pico Bioanalyzer assay. FU = fluorescence units measured by Bioanalyzer.